

# Vision<sup>6</sup> for Windows

## Microsoft Windows Installer Instructions

You can use Microsoft Windows installer service (Msiexec.exe) and a package file (vision.msi) to install Vision6 version 6.1 on Windows 2000 and XP. Windows 98 also supports Microsoft Windows Installer technology, but requires that you install it separately.

Before Vision installation, verify that the Install Shield script engine is installed on the computer. To install ISScript1050, type:

```
msiexec /qn /i <pathname>\ISScript1050.Msi
```

where <pathname> is the directory path that contains the package **ISScript1050.Msi**.

### Install Vision6 version 6.1

To install the Vision package file locally on a Windows-based computer, open the **Command Prompt** window and type the appropriate command line parameters. For example, to install Vision6 version 6.1 in quiet mode (no user interaction) on a teacher computer, type:

```
msiexec /qn /i <pathname>\vision.msi MESETUPTYPE=MASTER MESERIAL=<serial number>  
USERNAME=<Teacher> COMPANYNAME=<Lincoln High School>
```

where <pathname> is the directory path that contains the package **vision.msi**, <serial number> is your license key, and <Teacher> and <Lincoln High School> are user defined.

### Upgrade Vision6 to version 6.1

To upgrade a computer that is running Vision6 version 6.0 to version 6.1, type:

```
msiexec /qn /i <pathname>\Vision.msi REINSTALL=ALL REINSTALLMODE=vomus IS_MINOR_UPGRADE=1
```

where <pathname> is the directory path that contains the package **vision.msi**.

**NOTE:** When you upgrade from a previous version of Vision, it is not necessary to add additional parameters.

### Uninstall Vision6 versions 6.0 or 6.1

To uninstall Vision6 versions 6.0 or 6.1, type:

```
msiexec /qn /x {832C0EFD-9F5B-4BC3-9B21-8EAF1280BE8B}
```

No other parameters are necessary.

This technology is intended primarily for use in systems that support remote installation via command line, such as Microsoft SMS, Altiris Deployment Solution, and others. The package file **vision.msi** may be placed in a shared directory as defined by these systems, and executed remotely on supported computers.

### Installation Parameters

For a list of Windows Installer parameters, type **msiexec** at the command prompt. Vision6 parameters are listed below for both teacher and student computers:

#### For Teacher Computers

| Property Name        | Meaning   | Possible values   | Default Value |
|----------------------|---|-------------------|---------------|
| MESETUPTYPE*         | Installation setup type for instructor computer (MASTER).   | MASTER            | empty         |
| MEMASTERPASSWORD     | Password required to start Vision from the teacher computer.  |                   | empty         |
| MESERIAL*            | License number required to activate Vision on the teacher computer.   |                   | empty         |
| MEENVIRONMENTSCHHEME | Configures Vision to run a complete configuration (DIDACTIC) or adjust itself to increase the speed of the program (SPEED). | DIDACTIC<br>SPEED | DIDACTIC      |

---

\* Required parameter

| Property Name          | Meaning  | Possible values | Default Value |
|------------------------|--|-----------------|---------------|
| MEIFADDRESS            | Networking Interface address.                                  | <IP address>    | 0.0.0.0       |
| USERNAME*              | Registered user name.  |                 | <i>empty</i>  |
| COMPANYNAME*           | Registered company or school name.                             |                 | <i>empty</i>  |
| MEDEFAULTCLASSROOMNAME | The name of the classroom that is created during installation. |                 | Classroom     |

#### For Student Computers

| Property Name    | Meaning  | Possible values                          | Default Value |
|------------------|--|--|---------------|
| MESETUPTYPE*     | Installation setup type for student computer (USER).   | USER                                     | <i>empty</i>  |
| MESTARTUPTYPE    | When Vision starts on the student computer: <ul style="list-style-type: none"> <li>• Before Windows starts (BEFORELOGON)</li> <li>• When Windows starts (STARTUP)</li> <li>• The student starts Vision (MANUAL)</li> </ul> | BEFORELOGON<br>STARTUP<br>MANUAL         | BEFORE LOGON  |
| MEIFADDRESS      | Networking Interface address.  | <IP address>                             | 0.0.0.0       |
| MEOPENENROLLMENT | Allows student to attend open enrollment classes.  | YES<br>Any other value is treated as NO. | <i>empty</i>  |

---

\* Required parameter